


Table of Contents

Part I	Introducing Hot Virtual Keyboard	1
Part II	How to buy Hot Virtual Keyboard	1
Part III	How to use Hot Virtual Keyboard	2
1	Using the on-screen keyboard	. 2
	Keyboard shortcuts settings	
	Customizing the keyboard type	
	Text tags	
5	Editing shortcut icons	. 8
Part IV	Settings	9
1	System	. 9
2	General	10
3	Appearance Theme	11
4	Keys	12
5	Show/Hide	13
6	Position	14
7	Zoom	14
8	Typing Aid	15
9	Gestures	16
10	Floating Window	17
11	Text Suggestions	17
12	Language Bar	19
13	Shortcut Icons	20
14	Sounds	20
15	Dependencies	20
16	Advanced	21
Part V	Action types 2	21
1	Hot Virtual Keyboard actions	21
2	Replace key or shortcut	22
3	Play a keystroke macro	22
4	Paste text	23
5	Run a program; open a document or folder	23
6	Open one or several Internet resources	24
7	Connect/Disconnect from a network	24
8	Audio control	24
9	Monitor control	25

	Index	44
3	Contact information	43
	License Agreement	
	FAQ - Frequently asked questions	
	Other issues	37
5	Command line parameters	36
	FAQ for developers	
3	How to activate different keyboards	33
2	How to lock all settings	33
1	How to show, close, fade, or move the on-screen keyboard	26
Part VI	Development	26
14	Block key or shortcut	26
13	Lock/Restart/Shutdown	26
12	Change the language or case	25
11	Perform a system action	25
10	Window control	25

1 Introducing Hot Virtual Keyboard

Hot Virtual Keyboard makes previous-generation on-screen keyboards look ancient. Type faster with configurable <u>gestures</u>, launch programs, browse the Internet, and run programmable macros with any of the 70 keyboards included with Hot Virtual Keyboard. The new virtual on-screen keyboard employs advanced typing techniques used in modern mobile phones and communicators, including <u>word autocomplete</u> allowing you to choose the right word with a single click after entering just one or two letters.



Users of Tablet PC, UMPC, Panel PC, Car PC and similar touch-screen devices will find Hot Virtual Keyboard indispensable. Use a mouse, touchpad or fingers for on-screen typing. With Hot Virtual Keyboard, you can type faster and more conveniently than by using built-in Windows On-Screen Keyboard. Use gestures for quickly performing repeat operations such as shifting the case of the letters, specify applications to hide Hot Virtual Keyboard from, and set your own hotkeys to launch programs or Web sites, run macros, and perform operations such as copy and paste.

The new virtual onscreen keyboard replaces Windows built-in Touch Keyboard with a much more advanced alternative. It's just as useful and as compatible as the native application. Supporting all languages and all installed keyboard layouts, Hot Virtual Keyboard is a truly international tool. Supplying over 70 pre-defined keyboard skins, the virtual on-screen keyboard allows you to create, customize and configure a unique new keyboard to your personal liking. Adjust colors and gamma, assign unique sounds to groups of keys, set shape of the keys and choose your own background.

Using a virtual on-screen keyboard does not have to be a hassle. Try Hot Virtual Keyboard, and you'll never go back!

2 How to buy Hot Virtual Keyboard

Hot Virtual Keyboard is distributed as Shareware. If you like Hot Virtual Keyboard and decide to keep it, you will need to purchase a product key. The trial version becomes activated when you enter the product key on your computer.

You can purchase the product key on-line either by credit card, PayPal, bank transfer or check.

For more information, please visit https://hotvirtualkeyboard.com/buy/

For detailed information on how to purchase and activate Hot Virtual Keyboard, please read the following topics carefully:

<u>License Agreement</u> <u>Order online</u>

3 How to use Hot Virtual Keyboard

Are you new to Hot Virtual Keyboard? Read Using the on-screen keyboard first!

That topic explains how to use virtual keyboard.

Do you have any questions? Read FAQ first.

If you have any problems with Hot Virtual Keyboard, please read Frequently Asked Questions.

3.1 Using the on-screen keyboard

The on-screen keyboard lets you enter text using a touchscreen, a mouse, or any other pointing device. Unlike a physical keyboard, the on-screen keyboard changes labels on its keys depending on the current input layout (language), which allows you to type without having a localized keyboard.

The on-screen keyboard also provides additional settings to help you enter text more quickly: <u>Text Suggestions</u>, <u>Gestures</u>, <u>Typing Aid</u>, <u>Show alternate characters or symbols</u>, and more.

The **icons of shortcut keys** used in Windows and in the current application are displayed on the keys of the on-screen keyboard. If you hover the mouse over a key with an icon, you can see a hint describing the shortcut's purpose. This way, you can quickly learn keyboard shortcuts, which will help you work much faster and easier.



You can forcibly show or hide the on-screen keyboard by pressing the corresponding keyboard shortcut (by default, **Apps**), or by selecting the **On-Screen Keyboard** item in the application's context menu.

For more details on configuring the appearance and behavior of the on-screen keyboard, see the On-Screen Keyboard section.

Tips and tricks

- You can use the Floating Window or the Floating Icon to quickly show or hide the on-screen keyboard.
- If you right-click a key on the on-screen keyboard, the upper case will be used for entering the character.
- If you click a key on the on-screen keyboard with the middle mouse button, the application will emulate a key press in combination with **Ctrl** key.
- You can manually create files with shortcut icons for applications used in your everyday work. If
 you create such file for an application frequently used in your company and copy it to several
 workstations, you will considerably increase the efficiency of the employees. For more details,

see the **Editing shortcut icons** section.

When the on-screen keyboard is used with a touchscreen, the arrow keys work as a <u>D-pad</u>.

See Also


How to install another language and keyboard layout

3.2 Keyboard shortcuts settings

A keyboard shortcut (also known as accelerator key, shortcut key, hot key, hotkey, key binding, key combo, etc.) is a combination of keys that you need to press simultaneously to perform a certain action.

Keyboard shortcuts are added, deleted, and edited in the **Keyboard Shortcuts Settings** window. You can open it in several ways:

- 1. Click the Hot Virtual Keyboard icon in the system tray.
- 2. Right-click the Hot Virtual Keyboard icon in the system tray to open the application's context menu. Then select the **Keyboard Shortcuts Settings** item in that menu.
- Press the keyboard shortcut that opens the Keyboard Shortcuts Settings window (by default, Win+CapsLock).



NEXT STEP: Specify the keyboard shortcut to be used. There are two ways to do it:

- 1. Switch to the **Key combination** field and press the desired key combination.
- 2. Use the mouse pointer to select the keys for the combination on the on-screen keyboard.

NEXT STEP: Use the **Action** field to select the type of the action to be performed when you press the specified shortcut key.

You can use the **Active** field to specify display modes the specified action should work in. For instance, you can disable the Win keys and enable additional shortcut macros (see <u>Play a keystroke macro</u> section) in full-screen mode. This way, you can apply special settings when playing a computer game.


LAST STEP: Specify advanced parameters for the selected action. See the list of all actions, their parameters and usage examples in the <u>Action types</u> section.

Tips and tricks

- All active keyboard shortcuts are shown on the on-screen keyboard. For more details, see the <u>Using the on-screen keyboard</u> section.
- If you assign a **label** for an action, this label will be displayed on the on-screen keyboard and in the hint instead of the action description.
- When you are specifying keyboard shortcuts, the left and right control keys (Shift, Ctrl, Alt, or Win) are processed differently. To use only the right Shift, Ctrl, Alt, or Win key in a keyboard shortcut, press the respective right key. To use both right and left keys, press the respective left key.
- To delete an earlier specified keyboard shortcut, select (None) in the Action type field.
- When specifying a keyboard shortcut, you can use almost any keys or key combinations, including NumLock, CapsLock, and Alt+Tab. However, the following keys and key combinations cannot be used: Sleep, WakeUp, Power, F-Lock, and Ctrl+Alt+Del.
- To print the list of keyboard shortcuts, select the Print List item on the File menu.
- If you create **several files** with different keyboard shortcut configurations, you will be able to switch between them at any time (for instance, to use a separate set of keyboard shortcuts for particular applications). You can specify and use a keyboard shortcut for switching between the files.
- You can add a set of keyboard shortcuts from another file. To do it, select the Add from File...
 item on the File menu, and then select the file with the keyboard shortcut set.
- You can add a set of standard keyboard shortcuts to your file. To do it, open the Settings dialog box, switch to the Keyboard Shortcuts section, and click the Add... button. You can also remove an existing set of standard keyboard shortcuts from your file by clicking the Remove... button in the same section.
- To use one set of keyboard shortcuts in workgroups, save the file containing this set to a
 network resource, and configure it to be used on each workstation.

3.3 Customizing the keyboard type

You can customize the size of the on-screen keyboard, as well as the arrangement, appearance, and size of its keys.



To edit the on-screen keyboard, open the **Settings** dialog box, select the **On-Screen Keyboard** item, and then click the **Edit...** button. By default, the current keyboard type will be opened. To edit another keyboard type, click the **File** menu, and then click **Open**.


When editing the keyboard, you can use two types of virtual keys:

- **Square** keys are used by default. Specify only two points for them: the upper-left corner and the lower-right corner. You can use the **Width** and **Height** fields for such keys.
- **Keys consisting of lines** can take any shape. To configure them, use the **Points** table to specify all points that should be joined by lines, one by one. The last line will be automatically drawn between the first and last points. If necessary, you can use lines to draw a circle or oval. Look at how the **Enter** key is specified on the standard keyboard. Actually, it is one key, though displayed as two keys. The point [-1, -1] means that the points of one key end and the points of the next key start.

You can specify all parameters for the keys via the fields in the lower part of the window. When editing the keyboard, you can use the following features:

- Use the mouse pointer to select several keys at once by holding down the Shift key.
- Use the arrow keys to **resize** one or more selected keys by holding down the **Shift** key.
- Use the arrow keys to change the position of one or more selected keys by holding down the Ctrl key.
- Change any label. The new label will be displayed on the keys instead of the standard label or character. For instance, you can assign the "Customers" label to the F2 key. You can also change the font of the text or use special characters.

Assigning an image to any key of the on-screen keyboard



Picture (Normal, Hover, Pressed)

You can assign an image to each key state, or use the same image for all key states.

- Normal The key in its normal state
- **Hover** The highlighted key, when the mouse pointer hovers over it
- Pressed The key when pressed

Set borders

You can set borders for the picture on the key. When the application resizes the picture, the borders will not change.

Color (Normal, Hover, Pressed)

A key fill color, which is used only if the Picture setting is not used.

Font color (Normal, Hover, Pressed)

You can specify the font to be used for each key state. Font colors can be set even if no images are assigned to keys in the previous fields. If you keep the default setting, the application will use the color values from the theme's settings.

Transparent

To let the key behind the image show through the image background, select the **Transparent** check box. To make the image background opaque, unselect the **Transparent** check box.

Note: The Transparent property works only for images in the Bitmap format.

Show as background

If this option is on, key labels and hotkey icons will be rendered on top of the key image. Otherwise labels and icons will not be shown on the key.

Draw a border around a key

This option comes in handy if the image completely replaces the default style of the key. For example, see the *SkinMulticolor* keyboard.

Resize with a key

If this option is on, the image will be resized when the key size changes.

Fit width, Fit height

If this option is on, the width and/or height of the image will always be equal to the width and height of the key it was assigned to, respectively.

Additional keyboard settings

If you select this keyboard, Hot Virtual Keyboard will change the specified settings:

- Change the Fit width option regardless of the application's settings
- Change the <u>Lock aspect ratio</u> option regardless of the application's settings
- Always move the keyboard to the lower edge of the screen
- Always display labels and icons in the <u>center of keys</u>
- Always <u>transparent</u> keyboard background
- Fixed font size for all key labels (if empty, use the one from the application's settings)
- Dividing points This option is used when the keyboard size changes. The keyboard splits
 along the specified points, and the keys slide in opposite directions.

States:

■ - Don't change□ - Turn off☑ - Turn on

Tips and tricks

You can use the image or photo of a keyboard to edit a new on-screen keyboard according to it.

To do it, select the **Add Background** command on the **Edit** menu sand open the necessary image file. After configuring the keyboard, you can remove the image by selecting the **Clear Background** command on the **Edit** menu.

- It might be easier to create a new keyboard if you use an existing one as a basis. To do it, select the keyboard that looks mostly like yours, and save it under a different name by selecting the **Save As...** command on the **File** menu.
- Right-click the on-screen keyboard while editing it to add another point with the cursor coordinates to the currently edited key.
- When configuring complicated keys, it might be easier to use a **txt** file containing the entire information about the keyboard. Keyboard files are stored in the **Keyboards** subfolder.
- All modified keyboard txt files are stored in the Application Data folder. You can see the full
 path in the caption of the Edit Keyboard Type window (for example, "C:\Documents and
 Settings\UserName\Application Data\ComfortSoftware\Hot\VirtualKeyboard\Keyboard\"). You
 can move files from this folder to the Keyboard subfolder of the application installation folder.
- To delete an existing keyboard type, delete the file with its description from the Keyboards subfolder.
- To create a few keys with the same action assigned to them, add the point [-1, -1] to the points list. This special point means that the points of one key end and the points of the next key start. Some on-screen keyboards have two space bars or two Enter keys created using this method.

See Also

How to install another language and keyboard layout

3.4 Text tags

These types of macros are used if you have configured plain text templates or the Paste Text action.

<KEY shortcut>

Press the key combination. Keystrokes will be emulated inside the text (see the key identifier list). Use + (the plus sign) to specify a keyboard combination. You can specify a key code in the hexadecimal format by using \$ (the dollar sign). For instance, \$20 is Space, and \$1B is Escape. Sample keyboard combinations:

- <KEY WIN+R>regedit<KEY Enter> Start the registry editor.
- Login<KEY TAB>password<KEY ENTER> Enter the login and the password.

<INPUT>

This tag adds the ability to enter text from the keyboard that will be inserted into the text template.

<SOMEOF>...</SOMEOF>

Select random text from the lists enclosed in the **<CS>** and **</CS>** tags. You can embed these macros. Simple examples:

- <SOMEOF><CS>1</CS><CS>2</CS></SOMEOF> Inserts "1" or "2".
- <SOMEOF><CS>hi<SOMEOF><CS>1</CS><CS>2</CS></SOMEOF></CS><CS>bye
 <SOMEOF><CS>1</CS></SOMEOF></CS></SOMEOF> Inserts "hi1", "hi2", "bye1", or "bye2".

<POPUP>...</POPUP>

Show popup menu. Select text from the lists enclosed in the **<CS>** and **</CS>** tags. You can insert this tag inside each other. Simple example: <POPUP><CS>Hi</CS><CS>Hello</CS></POPUP> – Inserts "Hi" or "Hello".

<FILE filename>

Inserts text from the specified file (if exists) into the specified position.

<SELECTION>

Inserts the text currently selected in the active application.

<CLIPBOARD>

Inserts the text from the clipboard.

<SCRIPT>

```
This tag allows you to perform various functions from your JavaScript, for example: 
<SCRIPT> 
<FILE>Common.js</FILE> 
<FUNCTION>DoublingSlashes</FUNCTION> 
<PARAM><SELECTION></PARAM> 
</SCRIPT>
```

<DATETIME format>

Inserts date and time in the specified format (see the <u>format list</u>). You can get the date shifted by a certain number of days, weeks, months. Use the following format: +d, -d, +d1, -d1, +d2, -d2, +d3, -d3, etc. - Shift by one day, two days, three days, and so on. (y -

year, w - week, m - month, d - day, h - hour, n - minute)

Note: You can specify the position of the text cursor after the text is pasted by placing | (the pipe character) there.

3.5 Editing shortcut icons

Shortcut icons are displayed on the on-screen keyboard. A separate set of shortcut icons is displayed for each application.

Since applications use different mechanisms for storing shortcut icons, it is impossible to detect them automatically. So the Comfort Software Group uses its own sets of shortcut icons for each application. You can configure shortcut icons for any application (or Windows).

To edit shortcut icons, open the **Settings** dialog box, select the **Shortcut Icons** item, and click the **Edit shortcut icons** button.

By default, the Win* icon file is edited. To edit a different icon file, click the **File** menu, and then click **Open**.

Start the application you want to create icons for and select the name of its executable file in the **File name** drop-down menu. After that, the **Main window class name** and **Application name** fields will be filled in automatically.

The **File name** and **Main window class name** fields are used to determine which application is active. You can specify both fields or only one of them.

The **Application name** field is used for information about a specific application. Enter your details (for example, "Awesome App by John Doe (john@doe.com)").

To add a new icon, specify the keyboard shortcut in the **Key combination** field, or select it on the on-screen keyboard.

After that, you can add the icon in the following ways: load it from a file, capture the screen, or paste an image from the clipboard. If you add an icon by capturing the screen, fill all the area that you do not need with the **Fuchsia** color, and select that color in the **Transparent color** field. To see if the icon is good,

try selecting another style (for instance, black).


Finally, you can specify a hint to be displayed when you hover the mouse pointer over the key with the icon on the on-screen keyboard. You can use only one language, preferably English.

Note: All files with sets of shortcut icons are stored in the Icons subfolder.

4 Settings

When developing Hot Virtual Keyboard, we tried to keep the number of additional settings to a minimum and left only those that are truly necessary.

To open the Settings dialog box, right-click the Hot Virtual Keyboard icon in the system tray and select the **All Settings** item in the context menu.



4.1 System

The system settings define the interaction between Hot Virtual Keyboard and Windows.

Language

The language of the Hot Virtual Keyboard user interface. To change the language of the on-screen keyboard, <u>install another language or keyboard layout in your system</u>.

Run Hot Virtual Keyboard at Windows startup

If you check this checkbox, Hot Virtual Keyboard will be automatically launched when the system is started.

Show keyboard on logon screen

If you check this checkbox, the on-screen keyboard will be shown before any user logs into the system. A separate instance of the application, possibly with different settings, will be launched for that on-screen keyboard (see <u>FAQ for developers</u> section).

Disable system touch keyboard and handwriting panel

You can turn off the system Touch Keyboard that appears when you use a touchscreen. **Note:** Windows 7 and above.

Show the Hot Virtual Keyboard toolbar in the taskbar

Checking this checkbox will add the application's toolbar with one button onto the taskbar. You can use this button to launch the on-screen keyboard. **Note:** Not supported on Windows 11.

Set high priority for Hot Virtual Keyboard

Check this checkbox if any features of Hot Virtual Keyboard are unstable on your system.

Hide the Hot Virtual Keyboard icon in the system tray

If this checkbox is checked, the application's icon will not be shown in the system tray.

Add to the Windows context menu

Checking this checkbox will add the **Assign Keyboard Shortcut** item to the Windows context menu. You can select that item to assign shortcut keys for quick access to applications, documents, and other files.



4.2 General

The application displays a virtual keyboard on the computer screen, so that you can type using a pointing device or touchscreen.

Keyboard type

You can select a keyboard type. Each keyboard can have its own arrangement of keys. A special style has been defined for some keyboards. To edit any keyboard, select it and click the **Edit...** button. The keyboard layout changes depending on the current input language. You don't have to create your own keyboard for each language.

When I enter a password don't show which keys are tapped

If this checkbox is checked, key pressing will not be shown on the on-screen keyboard when the focus is on a password entry field. The Text Suggestions window also will not be shown.

Type characters when keys are released

If this checkbox is checked, characters will be typed when you raise your finger from the surface of a touchscreen or release the mouse button. Otherwise characters will be typed as you touch or click a key, just like with a regular keyboard. This option is especially useful in combination with the settings below.

Note: This feature doesn't work if the **Enable key repeat** option is on.

Enable key repeat

When a key is pressed and held, the keyboard types and continues to type the appropriate symbol at regular intervals until the key is released. This is the common behavior for a hardware keyboard. So you can use the on-screen keyboard for playing games on your mobile PC with a touch-screen. If you turn it on, the **Gestures** and **Type characters when keys are released** features will not work.

Show a tip over a pressed character key

If this checkbox is checked, pressing a key will cause a small window with an enlarged version of the corresponding character to pop up. This option is especially useful in combination with the previous option.

Show alternate characters or symbols

With this option on, Hot Virtual Keyboard will show alternate characters when you press and hold a key. The selected character will be entered when you release the key.

You can edit the list of alternate characters by editing the *AlternateSymbols.txt* file in the *Data* subfolder.

Note: This feature doesn't work if the **Enable key repeat** option is on.

Appearance delay (msec)

The delay between the pressing of a key and the appearing of the list of alternate characters.

Expert Settings

Show while holding down the key

Check this checkbox to show the keyboard when you hold down one of the selected keys: Shift, Ctrl, Alt, or Win.

Appearance delay (msec)

The delay between the pressing of a control key and the appearing of the on-screen keyboard.

Repeat delay (msec)

The amount of time that elapses before a character repeats when you hold down a key.

Repeat rate (characters per second)

The speed at which a character is repeated when you hold down a key.

Mouse pointer

There are three mouse pointer types that you can use: Standard (Arrow), Hand, or Invisible.

Show key characters in the UPPER CASE

If this option is on, key characters will be displayed in the upper case regardless of the state of the Shift and CapsLock keys.

4.3 Appearance Theme

By using a theme, you can change a wide range of visual elements, including colors, drawing styles, fonts, etc.

Style

A color scheme.

To edit any color scheme, select it and click the **Edit...** button (a new **Custom** scheme will be created). To edit a color, click the object and choose a color. You can assign an image to each key state, or use the same image for all key states.

Key states:

- Normal The key in its normal state
- Hover The highlighted key, when the mouse pointer hovers over it
- Pressed The key when pressed

Style of drawing

This style can be Normal, Gradient, or Tube Gradient.

Native style of the window

Checking this checkbox will instruct the application to use the native Windows style.

Rounded corners

Check this checkbox to make the application use the rounded style. If you do it, the rounding of windows' corners and buttons will be turned on.

Common opacity

You can adjust the opacity of the on-screen keyboard.

Background picture

You can select an image file (for example, a photo) to be used for the background. To remove the background image, simply clear the filename in the text field.

Characters font

The font for characters displayed on the on-screen keyboard.

Font

The font for labels displayed on the on-screen keyboard.

Icon

The icon for the on-screen keyboard in the system tray, the toolbar, the <u>floating window</u>, and <u>floating icon</u>.

4.4 Keys

Use these settings to adjust the look of keys and their labels. You can change the appearance of any key in the keyboard editing mode.

Show labels and icons in the center of keys

This option comes in handy if you use only one input language.

Show keyboard layout by default

The layout or language that is used to display key names in the upper-left corner.

Show symbols accessible via Shift when Shift is not pressed and font is not large

If the key size and font allows, all numerical keys will contain characters that are typed in combination with the Shift key.

Show symbols accessible via Ctrl and Shift+Ctrl

This option lets you display the characters that become available when you press Ctrl or Ctrl+Shift. As a rule, such key combinations are not used for text entry.

Color finger areas

You can highlight keys to learn touch typing. The keys will be highlighted in a different color for each finger.

Labels on system keys depend on the currently selected input language

You can change the labels displayed on these keys: Backspace, Tab, Enter, Shift, Ctrl, Alt, AltGr, Pause, Esc, PgUp, PgDn, End, Home, Arrows, PrtScr, Ins, Del, Apps, Win, Caps Lock, Num Lock, and Scroll Lock.

Show the state of Caps Lock, Num Lock and Scroll Lock keys

This option lets you display these keys as pressed if the respective mode is on (that is, if the respective indicator is lit on the physical keyboard).

4.5 Show/Hide

Show the on-screen keyboard when the text cursor is visible

If this checkbox is checked, the on-screen keyboard will appear when the text cursor is placed in a text field. Some applications draw the text cursor in their own way and do not provide information about its state. In this case, you can open the keyboard by pressing a hotkey or clicking the keyboard icon. You can also install a Browser Extension.

Show only when you click or tap a text box

If this checkbox is checked, the on-screen keyboard will appear when you click or tap a text box. If you activated application and the text cursor is visible, the keyboard will be hidden until you click a text box.

Extensions

You can install a browser extension to make the on-screen keyboard appear when the cursor is placed inside a text field. The extension will add keyboard-related information to the browser caption, and the application will monitor the caption for changes.

Hide the on-screen keyboard when typing on a physical keyboard

If you check this checkbox, the on-screen keyboard will disappear when you press a key on a physical keyboard; the on-screen keyboard will appear again when you touch the touchscreen, or call the on-screen keyboard by pressing a hotkey or clicking the keyboard icon.

This setting also hides the keyboard when you attach "Cover Keyboard". If your attachable keyboard doesn't hide the on-screen keyboard, please contact our support team.

Three finger tap on your touchscreen: Show/Hide

A three-finger tap on your touchscreen will toggle the visibility of the on-screen keyboard. This feature doesn't work in some applications. **Note:** Windows 8 and above.

Animate the launch of the on-screen keyboard

When the keyboard is started, it will appear on the screen by sliding up or down from under the specified screen border. When the keyboard is closed, it will slide under the specified border.

Auto hide

This option lets you hide the keyboard after the time specified in the **Disappearance delay** field expires.

Disappearance delay (msec)

The delay between the last pressing of any key and the disappearing of the on-screen keyboard.

End state

The on-screen keyboard can be transparent but not hidden totally. For example, you can set 5% opacity as the end state.

4.6 Position

Using these settings, you can specify the location of the on-screen keyboard.

Lock

Prevents the keyboard from moving.

Show the on-screen keyboard next to the text entry area when possible

Some applications draw the text cursor in their own way and do not provide information about its position (these are Firefox, OpenOffice, CorelDRAW, etc.). In this case, the keyboard will be shown in the bottom of screen.

Note: This feature doesn't work when you set the Docking setting.

Moves and sizes the active window

If the active window is under the on-screen keyboard, Hot Virtual Keyboard sizes and moves it in view. Unlike the **Docking** setting, it only changes the active window and cannot change the web browser in kiosk mode.

Docking

You can dock the keyboard at the top or bottom of the screen. If you dock the keyboard, the available desktop space will be reduced. Other applications' windows and desktop icons will be rearranged to adjust to the change.

Do not overlap the taskbar

The taskbar is taken into account when moving the keyboard to the edge of the screen if this setting is enabled.

Default position

When the on-screen keyboard appears, it will be automatically moved to the specified position (even if it had been moved elsewhere). If the user moves the keyboard to any location on the screen, it will remain at that location until disappears.

You can change this setting for any keyboard in the <u>Edit Keyboard Type</u> window. So your keyboards will have different positions on the screen when you switch between them.

The keyboard position changes even if the **Lock** setting is set.

Touch with two fingers to move

To move the on-screen keyboard, touch it with two fingers, and move them in the same direction. **Note:** Windows 7 and above.

4.7 **Zoom**

You can zoom in to get a close-up view of your keyboard, or zoom out to see more of the desktop. This feature lets you change the keyboard size without editing it.

Fit width

You can automatically scale the on-screen keyboard to match the screen width. This feature is useful if you frequently switch the screen between the portrait and landscape modes.

Width

The keyboard width scaling ratio. You can resize the keyboard window in the usual manner, by dragging its edge with the mouse.

Fit height

You can automatically scale the on-screen keyboard to match the screen height. If this option is used together with **Fit width**, the keyboard will fit the screen size.

Height

The keyboard height scaling ratio.

Lock aspect ratio

If this ratio is locked, the keyboard's width will be scaled in the same proportion as its height (and vice versa, the height will be scaled in the same proportion as the width).

Lock window size

You can prevent the keyboard from resizing.

Pinch or stretch to zoom when using a touchscreen

To zoom in or out, touch the on-screen keyboard with two fingers and then move the fingers toward each other (pinch) or away from each other (stretch). **Note:** Windows 7 and above.

4.8 Typing Aid

Additional settings for comfortable typing.

Double taping the space bar will insert a period followed by a space

You can insert a period followed by a space by pressing the space bar twice.

Capitalize the first letter of each sentence

If one of the specified characters is entered, the Shift key will be pressed automatically.

Delete a space before

If any of the characters on the list is entered and there are any spaces before that character, the spaces will be removed.

Add a space after

If any of the characters on the list is entered, a space will be added after that character.

Add a space before

If any of the characters on the list is entered and there is no space before that character, a space will be added before it.

Use all uppercase letters when I double-tap Shift

The keyboard holds the Shift key when you double-click the Shift key. It will stay down until pressed again.

Hold down Shift, Ctrl, Alt and Win key until pressed again

If a key is pressed for the first time, it will stay down until pressed again.

Enable AutoClick

If you hover the mouse over a key, it will be pressed automatically with the specified interval between key presses. This feature may be useful for persons with certain disabilities.

AutoClick delay (msec)

The time that passes before a mouse click is done at the mouse pointer's current position.

4.9 Gestures

Gestures support (to quickly enter capital letters, spaces, etc.) with adjustable sensitivity:



If you check the **Use gestures** checkbox, characters will be entered when you raise your finger from the surface of a touchscreen or release the mouse button. Otherwise characters will be entered as you type, just like when you use a regular keyboard.

You can use a mouse or your fingers to perform a gesture:

- Touchscreen: Touch the screen with one finger and move a short distance.
- **Mouse:** Mouse gestures work by holding the left mouse button, moving the mouse a certain direction, then letting go of the button.

You can modify actions for each swipe type, or disable only some of them by selecting the (None) item.

Note: This feature doesn't work if the **Enable key repeat** option is on.

You can specify gestures for any of the following actions:

- · Press any key
- Press a key with the Shift key
- Delete word to left
- Delete word to right
- Ctrl+Home shortcut
- Ctrl+End shortcut
- Ctrl+Z shortcut (Undo)
- Move the on-screen keyboard to a screen border
- Close the on-screen keyboard
- Text Suggestions on/off
- Move the caret left one word
- Move the caret right one word
- Switch the input language or layout
- Show settings

4.10 Floating Window

There are two different windows that you can use to open the on-screen keyboard.

The first window, which can be placed anywhere on the screen, allows you to show or hide the on-screen keyboard.

The second window is displayed as an icon located next to the text cursor. If there is no text cursor on the screen, this window will not be shown.

You can resize any of these windows, adjust their transparency, or make them automatically disappear when the keyboard is displayed on the screen.

Auto hide

You can hide these windows when the on-screen keyboard is visible, and show them when the keyboard is hidden.

Transparent background

Show icon and label only.

Show the floating icon for the on-screen keyboard next to the text cursor

You can make a floating icon appear automatically when you tap a screen location where you want to insert your text. To open the on-screen keyboard, tap the floating icon.

Some applications draw the text cursor in their own way and do not provide information about its position. (These are Firefox, Google Chrome, OpenOffice, CorelDRAW, etc.) In this case, the floating icon will not be shown.

Note: You can change the settings of the floating window via its context menu.

4.11 Text Suggestions

As soon as you have typed a sufficient number of valid characters to equal or exceed the **Minimum Character Threshold**, the word list will be searched for all known words beginning with those characters. If any matching words are found, the Text Suggestions window will appear with those words; otherwise the window will not be displayed.

If you select any of the suggested words, it will be inserted into the text.

The order of words in the list depends on the statistics accumulated by Hot Virtual Keyboard. The application initially has predefined data on word frequency and word order for the most popular languages. These data are stored in the *Common* subfolder. When you type any text, Hot Virtual Keyboard memorizes the words that you use, so that later it can place the most frequently used ones in the beginning of the list. Which words are suggested also depends on the previously typed text. Any new words, which are not available in the installed dictionaries, are saved to the "custom.dic" file. To edit that file, select the file in the list, and then click the **Edit...** button. When you finish editing the file, click the **Read/Refresh word list** button.

The word usage statistics is kept separately from other data. To clear the statistics, click the **Reset Statistics** button.

Installing Dictionaries

The Text Suggestions feature uses files with the "dic" extension (for example, "en.dic"). These files are stored in the **Data directory** folder. To download a file for your language, click the **Download...** button. You can also create your own file with a word list. The file can contain any words or numerical values.

Show as a set of buttons next to the on-screen keyboard

With this option turned on, when the on-screen keyboard is visible, words will be displayed as a set of buttons; otherwise words will be displayed as a vertical list.

Align text left

If this check box is checked, the words in the "Text suggestions" window are aligned to the left, otherwise they are centered.

Auto hide

With this option turned on, the Text Suggestions window will be automatically hidden if no matching words have been found. Otherwise you can resize the Text Suggestions window or move it anywhere on the screen.

Show, hide and move with the on-screen keyboard

Checking this checkbox will make the word list behave like part of the on-screen keyboard. Otherwise the word list will be displayed next to the text cursor.

Minimum character threshold

This value defines how many characters of a word you need to type before the Text Suggestions window appears.

Number of displayed words

This value defines how many words will be displayed in the Text Suggestions window.

Appearance delay (msec)

The delay between the typing of valid characters and the appearing of the Text Suggestions window.

Add a space after I choose a text suggestion

The application can automatically type a space after you use word completion. This option is very handy as you won't have to press the space bar after each word. When you don't want to add a space automatically, right-click on the word.

Do not show words with 1 character remaining

If this checkbox is checked, nearly finished words will not be shown.

Show numbers

You can display shortcuts on the left side of the Text Suggestions window. This option lets you paste a word by using a numeric key.

Confirm with key

If words are displayed as a vertical list, you can select a word using the arrow keys, and then use the specified key to paste the selected word. If words are arranged in a horizontal line, the first (leftmost) word will be inserted.

Dictionaries

Learn new words

If this checkbox is checked, commonly used words will be saved to the "custom.dic" file. **Note:** The words that you enter are saved in the UTF-8 format.

Confirmation of the addition of words to the custom dictionary

With this option on, a confirmation window will be displayed for adding a new word to the "custom.

dic" file.

Disappearance delay (msec)

When this time expires, the confirmation window for adding a new word will disappear.

Confirm with key

You can press this key to confirm the adding of a new word to the dictionary.

Data directory

The folder containing dictionaries and user statistics.

Dictionaries

The dictionaries are ASCII files that can be edited directly like any other plain text files.

Read/Refresh word list

Click this button after editing a dictionary.

Reset Statistics

This button clears the user statistics. If the **Show text suggestions as I type** option is on, the statistics will be collected at all times. The statistics cannot be viewed or edited by the user, but only cleared.

Tips and tricks

- To remove a word directly from the custom dictionary, highlight it in the word list and press the
 Delete key. For this method to work, the Show as a set of buttons next to the on-screen
 keyboard option must be turned off.
- To disable common statistics for different languages, delete the files from the Common subfolder.

4.12 Language Bar



Visible

If this checkbox is checked, the language bar will be shown.

Lock the language bar

You can prevent the language bar from moving.

Show, hide and move with the on-screen keyboard

Checking this checkbox will make the language bar behave like part of the on-screen keyboard.

Kind of the language bar

- Language flag
- Language flag with a name
- Vertical list of flags
- Horizontal list of flags
- List of flags with names

Custom

Show label

You can display the "Switch the input language or layout" label next to the language flag in the custom view. The size of the flag depends on the size of the language bar: 16x16 or 32x32 pixels.

Opacity

You can adjust the transparency of the inactive language bar.

Note: You can change the settings of the Language bar via its context menu.

4.13 Shortcut Icons

Application shortcut icons shown on the on-screen keyboard can help you find the necessary shortcut.

Show Windows icons, Show active application icons, Show Hot Virtual Keyboard icons

These settings let you display the respective icons on the on-screen keyboard.

Show hints

You can show hints on the keyboard.

Show information about the availability of application shortcuts

If you check this checkbox, special marks will be shown in the lower-left corners of the keys on the on-screen keyboard. These marks indicate the availability of key combinations with control keys:

- Green with Ctrl
- Yellow with Ctrl+Shift
- Blue with Alt
- Red with Alt+Shift

See Also

Editing shortcut icons

4.14 Sounds

You can configure short sounds for different events, such as pressing a key on the on-screen keyboard. By default, sounds are turned on. You can turn them off via the application's context menu.

You can adjust the volume for the sounds. The application will apply that volume to all its sounds.

To select your own sound, click the Browse... button. You can use only Wave files.

4.15 Dependencies

Hot Virtual Keyboard changes the appearance of the on-screen keyboard and other things depending on which application is currently active.

How it works

If you switch to a particular application, Hot Virtual Keyboard will change the specified settings. When you switch back to the previous application, Hot Virtual Keyboard will restore the original settings.

Each setting in the list changes depending on the selected mode:

- Don't change the setting (use the setting defined in the Settings window)
- Turn off the setting
- Turn on the setting

In addition to the settings in the list, you can change the look of the on-screen keyboard and the set of hotkeys for a selected application.

4.16 Advanced

Check for Updates

Scheduled check for updates. To disable checking for updates, select the Disabled item.

Num Lock state

This option lets you keep or change the NumLock state when Hot Virtual Keyboard is started.

Numeric keys on the keypad even if Num Lock is off

This option may be handy if you work on a laptop and use both its keyboard together and a standard keyboard connected to the laptop. If you turn NumLock on, some letter keys on the laptop keyboard will work as digital keys. If you turn NumLock off, you will be unable to use the NumPad keys on the standard keyboard to enter digits. By checking this checkbox, you can easily overcome the limitation imposed by the NumLock key.

Save to File...

Click this button to save all settings to the INI file.

Load from File...

Click this button to load all settings from the INI file. You can also load settings from the INI file by using the <u>/RESTORE command line parameter</u>.

5 Action types

To use Hot Virtual Keyboard more effectively, please familiarize yourself with the predefined action types.

You can assign a specific sound to each action.

If you assign a **label** for an action, this label will be displayed on the on-screen keyboard and in the hint instead of the action description.

5.1 Hot Virtual Keyboard actions

You can use this group of actions to configure shortcut keys for the Hot Virtual Keyboard features.

Close keyboard

Close the on-screen keyboard window.

Show the keyboard shortcuts settings window

Opens the keyboard shortcuts settings window. For more details, see the <u>Keyboard shortcuts</u> settings section.

Toggle the visibility of the on-screen keyboard

Shows or hides the on-screen keyboard. For more details, see the <u>Using the on-screen keyboard</u> section.

Activate the next keyboard type

Loads the next keyboard from the list of keyboards. To configure that list, click the **Set the List of Keyboards** button.

Show settings

Opens the application's **Settings** window.

Text Suggestions on/off

Enables or disables the Text Suggestions feature. For more details, see the <u>Text Suggestions</u> section.

5.2 Replace key or shortcut

You can assign an action of this type to a key combination, though it is mostly used to replace a key combination by a single key.

Usage examples

- You can create keys on the on-screen keyboard for frequently used actions: Ctrl+C (Copy),
 Ctrl+V (Paste), Ctrl+Z (Undo), etc.
- You can remove function keys (F1, F2, etc.) from the on-screen keyboard, and use key combinations (Fn+1, Fn+2, etc.) instead.
- You can emulate a mouse click by pressing a key (for example, set the **AltGr** key as **Right Button**).
- You can turn your regular keyboard into a multimedia keyboard by configuring shortcut keys
 to behave as the keys unavailable on your keyboard: SEARCH, FAVORITES, HOME,
 NEXT_TRACK, PREV_TRACK, STOP, PLAY_PAUSE, etc.

5.3 Play a keystroke macro

A keystroke macro is a sequence of keystrokes or key combinations. Just specify once which keys should be pressed, and Hot Virtual Keyboard will duly repeat these keystrokes as many times as needed.

You can use the actions of this type to:

- Create keyboard shortcuts practically for any actions. One keyboard shortcut can replace the need to press several keys.
- Fill out forms.
- Enter your username and password.
- Quickly print a predefined number of document copies.
- And much more. If you frequently do the same routine operation, think about automating it.
 Keep in mind that practically any action can be done without using the mouse.

To start recording a macro, click the **Record** button.

To stop recording the macro, press the Pause key, or click the Record icon in the system tray.

When you are recording a macro, all your keyboard actions are saved to a table with the following fields:

Delay before the next action.

- **Event type** whether the key is pressed down or released.
- **Key** code.
- The sign that the key is an **extended** one.

You can edit a previously recoded macro, or create a new macro without recording it. To do it, click the **Edit** button.

Having recorded a macro, you can specify advanced parameters defining how it will be played:

- Play speed.
- The number of repetitions.
- The name of the process that should be activated before starting the macro. For example, you
 can make the window of Windows Media Player active before the macro is played. If Windows
 Media Player is not running at the moment, the macro will not be played.

You can **stop playing** the macro anytime. Just press the **Pause** or **Esc** key, or click the **Playback** icon in the system tray.

5.4 Paste text

You can use the Paste Text action to:

- Create a separate key on the on-screen keyboard for any character or text string, such as @ or ".com".
- Quickly paste frequently used text fragments: greetings, cliches, email addresses, URLs, logins, and passwords.
- Quickly fill in web forms and registration dialog boxes.
- Type special characters that are difficult to enter using the regular keyboard.

Tips and tricks

- You can **protect** your data with strong 448-bit Blowfish **encryption**.
- All text is saved in the Unicode format, so you can use any characters.
- You can add various tags to the text. See how to use tags in the <u>Text tags</u> section.
- You can specify the position of the text cursor after the text is pasted by placing | (the pipe character) there.

5.5 Run a program; open a document or folder

You can use actions of this type to:

- Quickly start your favorite applications.
- Open frequently used folders and drives: My Documents, CD/DVD drive, etc.
- Open frequently used documents and network drives.
- Hide a file from your boss or kids, leaving access to it only via a keyboard shortcut.
- Clear your desktop from a pile of shortcuts, as now you can use the on-screen keyboard instead.

Program, folder or document Name

You can specify one or more programs in a separate line.

You can also run a program with additional parameters. **For example:** "C:\Program Files\Internet Explorer\iexplore.exe" -nohome

You can use <SELECTION> and <CLIPBOARD> tags for actions. For example: C:\voice.exe <SELECTION>

Start in folder

Enter the start-in folder for the program here. If you use the **Add...** button to find a program or document that you want to open with this action, the **Start-in folder** field will be filled automatically with the folder where the selected file is located.

Turn on the **Switch to the already launched program** option, and you will no longer need to check whether this program is already running or not.

Note: Select the <u>Add to the Windows context menu</u> check box in the Hot Virtual Keyboard settings, and you will be able to assign a shortcut key by right-clicking the shortcut of the program you are interested in and selecting the **Assign Keyboard Shortcut** item in the context menu.

5.6 Open one or several Internet resources

You can use actions of this type to:

- Open one or more websites that you visit every day (news, weather, forums, entertainment, etc.)
 with a single keystroke.
- Quickly open your favorite search engine: www.yahoo.com, etc.
- Create new email messages with the specified "To:" address. Just enter a string like *mailto*: support @google.com in the **Open URL** field.
- Quickly open the page of your corporate server.

You can use <SELECTION> and <CLIPBOARD> tags for actions. **For example:** https://translate.google.com/#fr/en/<SELECTION>

5.7 Connect/Disconnect from a network

Using this action type, you can easily set up a dial-up or ADSL connection.

After establishing a connection, you can close it anytime by pressing the same hotkey again.

Note: The connection must be already defined in "Windows Networking."

5.8 Audio control

You can configure shortcut keys for controlling the **sound volume** of the default device: **turn it up, turn it down, mute, or unmute**. Whenever you perform any of these actions, a slider (like that on a TV screen) will be displayed in the lower part of the screen.

Audio devices in Windows are the ones that you can use to play or record audio. This means that each time you listen to your favorite songs or talk on the microphone, you are using audio devices. When you listen to music (or any sound that comes from your computer), you are using the playback functionality that lets you hear the sounds in your speakers or headphones. An audio device can also record sounds coming from your microphone (for example, your voice) or from your computer (for example, the sounds produced by your playback device), thus providing the recording functionality.

Use these actions to change the default device: Change the default playback device and Change the default recording device.

5.9 Monitor control

You can configure shortcut keys for controlling your display: to turn your monitor on or off, to start a screen saver, or to open the *Display Settings* window.

5.10 Window control

You can specify keyboard shortcuts for any of the following actions:

- Minimize the active window
- Maximize/Restore the active window
- Close the active window or application
- Hide the active window or application
- Show the last hidden window
- Minimize the active window to the system tray
- Set the active window to be always on top (on/off)
- Terminate the active program

You can find the list of hidden windows in the context menu of Hot Virtual Keyboard. To show a hidden window, select its name in that list.

If you want some applications to keep running without being shown on the screen (for example, computer games), you can easily hide their windows.

Note: Some applications cannot be hidden because of their complex window structure. Instead of the window that you can see, only their service window is hidden.

5.11 Perform a system action

You can specify keyboard shortcuts for any of the following actions:

- Open the "Safely Remove Hardware" window
- Open Control Panel (Control Panel contains links to most of the tools used to configure various aspects of Windows)
- Open the "Date and Time" window
- Open the "Internet Properties" window
- Map network drive
- Disconnect network drive
- Empty recycle bin

5.12 Change the language or case

Using this group of actions, you can change the language, layout, or letter case of text.

You can specify keyboard shortcuts for any of the following actions:

- Change the input language or layout of the last typed characters
- Change the input language or layout of the selected text
- Switch the input language or layout
- Change language, layout or case
- Change the input language or layout to specified
- Change all the selected text to UPPER CASE
- Change all the selected text to lower case
- Change all the selected text to iNVERT cASE
- Change all the selected text to Sentence case.
- Capitalize Each Word of the selected text

- Use the specified input language or layout while holding down the key
- Change the input language or layout of the last typed word
- Change the input language or layout of the two lastly typed words
- Change the input language or layout of the three lastly typed words

5.13 Lock/Restart/Shutdown

You can specify keyboard shortcuts for any of the following actions:

- Lock this computer
- Log off
- Restart the computer
- Sleep
- Hibernate
- Shut down the computer
- Show the shut down dialog

5.14 Block key or shortcut

This action type allows you to block any key or key combination.

Usage examples

- You can block any key combinations: Alt+Tab, Alt+Esc, Ctrl+Shift+Esc, Ctrl+Shift, etc.
- You can block the Left Win and Right Win keys in computer games running in full-screen mode.
- You can block any keys, such as CapsLock, Insert, or NumLock. At the same time, you can
 check the Enable combinations with other keys checkbox to be able to use the features of
 the blocked keys:
 - Shift+CapsLock will be used instead of CapsLock.
 - Shift+NumLock will be used instead of NumLock.
 - Shift+Ins will paste text from the clipboard.

6 Development

How to show, close, fade, or move the on-screen keyboard

How to restrict access

How to activate different keyboards

FAQ for developers

Command line parameters

6.1 How to show, close, fade, or move the on-screen keyboard

You can use Windows Messages to manipulate the on-screen keyboard.

Like this:

```
WM_CSKEYBOARD = WM_USER + 192;
WM_CSKEYBOARDMOVE = WM_USER + 193;
```

```
WM_CSKEYBOARDRESIZE = WM_USER + 197;
// to show keyboard
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARD, 1, 0);
// to close keyboard
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARD, 2, 0);
// to fade keyboard
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARD, 3, 0);
// to toggle (show/hide) keyboard
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARD, 4, 0);
// to move keyboard (Left, Top - new position)
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARDMOVE, Left, Top);
// to resize keyboard
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSKEYBOARDRESIZE, Width, Height);
Visual Basic Sample Code
  Private Const WM_CSKEYBOARD = WM_USER + 192
  Private Const WM_CSKEYBOARDMOVE = WM_USER + 193
  Private Const WM_CSKEYBOARDRESIZE = WM_USER + 197
  Declare Function FindWindow Lib "user32" Alias "FindWindowA" (ByVal lpClassName As &
  'Code to show keyboard
  Dim hWnd As Long
  hWnd = FindWindow("TFirstForm", "hvkFirstForm")
  PostMessage hWnd, WM_CSKEYBOARD, 1, 0
  'Code to close keyboard
  Dim hWnd As Long
  hWnd = FindWindow("TFirstForm", "hvkFirstForm")
  PostMessage hWnd, WM_CSKEYBOARD, 2, 0
  'Code to move keyboard
  Dim hWnd As Long
  hWnd = FindWindow("TFirstForm", "hvkFirstForm")
  PostMessage hWnd, WM_CSKEYBOARDMOVE, 0, 0
  'Code to resize keyboard
  Dim hWnd As Long
  hWnd = FindWindow("TFirstForm", "hvkFirstForm")
  PostMessage hWnd, WM_CSKEYBOARDMOVE, Width, Height
■ C# Sample Code
  using System;
  using System.Windows.Forms;
  using System.Runtime.InteropServices;
  public const Int32 WM_USER = 1024;
  public const Int32 WM_CSKEYBOARD = WM_USER + 192;
  public const Int32 WM_CSKEYBOARDMOVE = WM_USER + 193;
  public const Int32 WM_CSKEYBOARDRESIZE = WM_USER + 197;
  [DllImport("user32.dll", EntryPoint = "FindWindow")]
  private static extern Int32 FindWindow(string _ClassName, string _WindowName);
  [DllImport("User32.DLL")]
  public static extern Boolean PostMessage(Int32 hWnd, Int32 Msg, Int32 wParam, Int32
```

```
Int32 hWnd = FindWindow("TFirstForm", "hvkFirstForm");
    PostMessage(hWnd, WM_CSKEYBOARD, 1, 0 ); // Show
    PostMessage(hWnd, WM_CSKEYBOARD, 2, 0); // Hide
    PostMessage(hWnd, WM_CSKEYBOARDMOVE, 0, 0); // Move to 0, 0
    PostMessage(hWnd, WM_CSKEYBOARDRESIZE, 600, 300); // Resize to 600, 300
■ Visual Basic 2008 (VB.NET) Sample Code
    Const WM_CSKEYBOARD = &H400 + 192
    Const WM_CSKEYBOARDMOVE = &H400 + 193
    Const WM_CSKEYBOARDRESIZE = &H400 + 197
    Declare Function FindWindow Lib "user32" Alias "FindWindowA" (ByVal lpClassName As &
    Declare Function PostMessage Lib "user32" Alias "PostMessageA" (ByVal hwnd As Intege
    'Open/show the Hot Virtual Keyboard
    Private Sub Button1_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARD, 1, 0)
    End Sub
    'Close the Hot Virtual Keyboard
    Private Sub Button2_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARD, 2, 0)
    End Sub
    'Move the Hot Virtual Keyboard; Move it first then show it
    Private Sub Button3_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARDMOVE, 200, 200)
           PostMessage(hWnd, WM_CSKEYBOARD, 1, 0)
    End Sub
    'Toggle the Hot Virtual Keyboard
    Private Sub Button4_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARD, 4, 0)
    End Sub
    'Fade the Hot Virtual Keyboard
    Private Sub Button5_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARD, 3, 0)
    End Sub
    'Change the keyboard type and show it
    Private Sub Button6_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
            'Change the Registry entry for the required keyboard
           {\tt My.Computer.Registry.SetValue("HKEY\_CURRENT\_USER\Software\ComfortSoftware\hvk", Institute of the computer of the computer
            'Open the keyboard
           Dim hWnd As Integer
           hWnd = FindWindow("TFirstForm", "hvkFirstForm")
           PostMessage(hWnd, WM_CSKEYBOARD, 1, 0)
    End Sub
    'Change to another keyboard type and show it
    Private Sub Button7_Click(ByVal sender As System.Object, ByVal e As System.EventArgs
            'Change the Registry entry for the required keyboard
```

```
My.Computer.Registry.SetValue("HKEY_CURRENT_USER\Software\ComfortSoftware\hvk",
      'Open the keyboard
      Dim hWnd As Integer
      hWnd = FindWindow("TFirstForm", "hvkFirstForm")
      PostMessage(hWnd, WM_CSKEYBOARD, 1, 0)
  End Sub

    □ C++ (CLR syntax) Sample Code

  using namespace System::Runtime::InteropServices;
  using namespace System::Security::Permissions;
  using namespace Microsoft::Win32;
  const System::UInt32 WM_USER = 1024;
  const System::UInt32 WM_CSKEYBOARD = WM_USER + 192;
  const System::UInt32 WM_CSKEYBOARDMOVE = WM_USER + 193;
  [DllImport("user32.dll")]
  extern IntPtr FindWindow(String^ lpClassName, String^ lpWindowName);
  [DllImport("user32.dll")]
  extern IntPtr PostMessage(System::IntPtr hWnd, System::UInt32 Msg, int wParam, int 1
  [assembly:RegistryPermissionAttribute(SecurityAction::ReguestMinimum, All = "HKEY_CU
  ....blah blah blah you normal code...
  void button1_Click(System::Object^ sender, System::EventArgs^ e)
      // Open/show the Hot Virtual Keyboard
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARD, 1, 0);
  void button2_Click(System::Object^ sender, System::EventArgs^ e)
          // close the Hot Virtual Keyboard
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARD, 2, 0);
  void button3_Click(System::Object^ sender, System::EventArgs^ e)
      //Move the Hot Virtual Keyboard; Move it first then show it
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARDMOVE, 200, 200);
      PostMessage(hWnd, WM_CSKEYBOARD, 1, 0);
  void button4_Click(System::Object^ sender, System::EventArgs^ e)
      //Toggle the Hot Virtual Keyboard
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARD, 4, 0);
  void button5_Click(System::Object^ sender, System::EventArgs^ e)
      //Fade the Hot Virtual Keyboard
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARD, 3, 0);
  void button6_Click(System::Object^ sender, System::EventArgs^ e)
      //Change the keyboard type and show it
```

```
System::Object ^kname="NumPad";
      //Change the Registry entry for the required keyboard
      RegistryKey ^key= Registry::CurrentUser->OpenSubKey ( "Software\\ComfortSoftware
      key->SetValue("KeyboardName",kname);
      //Open the keyboard
      IntPtr hWnd;
      hWnd = FindWindow("TFirstForm", "hvkFirstForm");
      PostMessage(hWnd, WM_CSKEYBOARD, 1, 0);
Java Sample Code
   * This file is heavily based on Jawin: <a href="http://jawinproject.sourceforge.net"
   * assumes ComfortSoftware keyboard is loaded...
   * /
  package client.keyboard;
  import java.io.ByteArrayInputStream;
  import java.io.IOException;
  import org.jawin.COMException;
  import org.jawin.FuncPtr;
  import org.jawin.ReturnFlags;
  import org.jawin.io.LittleEndianInputStream;
  import org.jawin.io.LittleEndianOutputStream;
  import org.jawin.io.NakedByteStream;
  public class ComfortSoftwareKeyboard {
      protected static final String COMFORT_SOFTWARE_WINDOW_NAME = "hvkFirstForm";
      protected static final String COMFORT_SOFTWARE_CLASS_NAME = "TFirstForm";
      protected static final int WM_USER = 1024;
      protected static final int WM_CSKEYBOARD = WM_USER + 192;
      protected static final int WM_CSKEYBOARDMOVE = WM_USER + 193;
      protected static final Call FIND_WINDOW = new Call("USER32.DLL", "FindWindowW",
      protected static final Call POST_MESSAGE = new Call("USER32.DLL", "PostMessageW"
      private static ComfortSoftwareKeyboard INSTANCE = new ComfortSoftwareKeyboard();
      public static ComfortSoftwareKeyboard getInstance() {
          return INSTANCE;
      protected int getWindowHandle() throws COMException, IOException {
          FuncPtr findWindow = null;
          findWindow = new FuncPtr(FIND_WINDOW.getDllName(), FIND_WINDOW.getFunctionNa
          NakedByteStream bs = new NakedByteStream();
          LittleEndianOutputStream leo = new LittleEndianOutputStream(bs);
          leo.writeStringUnicode(COMFORT_SOFTWARE_CLASS_NAME);
          leo.writeStringUnicode(COMFORT_SOFTWARE_WINDOW_NAME);
          byte[] b = findWindow.invoke(FIND_WINDOW.getParameterDescription(), FIND_WIN
                  ReturnFlags.CHECK_FALSE);
          LittleEndianInputStream leis = new LittleEndianInputStream(
                  new ByteArrayInputStream(b));
          int 1 = leis.readInt();
          findWindow.close();
```

return 1;

```
}
    public int move(int x, int y) throws COMException, IOException {
        int hWnd = getWindowHandle();
        FuncPtr postMessage = null;
        postMessage = new FuncPtr(POST_MESSAGE.getDllName(), POST_MESSAGE.getFunctic
        NakedByteStream bs = new NakedByteStream();
        LittleEndianOutputStream leo = new LittleEndianOutputStream(bs);
        leo.writeInt(hWnd);
        leo.writeInt(WM_CSKEYBOARDMOVE);
        leo.writeInt(x);
        leo.writeInt(y);
       byte[] b = postMessage.invoke(POST_MESSAGE.getParameterDescription(), POST_N
                ReturnFlags.CHECK_FALSE);
        LittleEndianInputStream leis = new LittleEndianInputStream(
               new ByteArrayInputStream(b));
        int l = leis.readInt();
        postMessage.close();
        return 1;
    }
    public int setVisible(boolean visible) throws COMException, IOException {
        int hWnd = getWindowHandle();
        FuncPtr postMessage = null;
        postMessage = new FuncPtr(POST_MESSAGE.getDllName(), POST_MESSAGE.getFunctic
        NakedByteStream bs = new NakedByteStream();
        LittleEndianOutputStream leo = new LittleEndianOutputStream(bs);
        leo.writeInt(hWnd);
        leo.writeInt(WM_CSKEYBOARD);
        leo.writeInt(visible ? 1 : 2);
        leo.writeInt(0);
       byte[] b = postMessage.invoke(POST_MESSAGE.getParameterDescription(), POST_N
                ReturnFlags.CHECK_FALSE);
        LittleEndianInputStream leis = new LittleEndianInputStream(
                new ByteArrayInputStream(b));
        int l = leis.readInt();
       postMessage.close();
        return 1;
    }
    public static void main(String[] args) throws Exception {
            ComfortSoftwareKeyboard keyboard = ComfortSoftwareKeyboard.getInstance()
            keyboard.setVisible(true);
            Thread.sleep(1000);
            keyboard.setVisible(false);
            Thread.sleep(1000);
            keyboard.setVisible(true);
            for (int i = 0; i < 100;i++) {</pre>
                keyboard.move(i, i);
        } catch (COMException e) {
         finally {
    }
}
class Call {
```

If you can't use Windows Messages then download and try these files:

https://hotvirtualkeyboard.com/files/ShowKB.exe

https://hotvirtualkeyboard.com/files/HideKB.exe

https://hotvirtualkeyboard.com/files/ToggleKB.exe

https://hotvirtualkeyboard.com/files/MoveTopKB.exe

https://hotvirtualkeyboard.com/files/MoveBottomKB.exe

https://hotvirtualkeyboard.com/files/MoveLeftKB.exe

https://hotvirtualkeyboard.com/files/MoveRightKB.exe

https://hotvirtualkeyboard.com/files/MoveKB.exe (Command line format: MoveKB.exe Left Top)

https://hotvirtualkeyboard.com/files/SetNameKB.exe (Command line format: SetNameKB.exe

KeyboardName)

If you are writing kiosk software using HTML, you can use the special JavaScript functions to control the on-screen keyboard.

With JavaScript, you can show, hide, or move the keyboard. Just use the special JavaScript functions to add keyboard-related information to the browser caption, and the application will monitor the caption for changes.

Download the file with JavaScript functions and examples from here: https://hotvirtualkeyboard.com/ commander.html

WM_CSKEYBOARDMOVE: Solving the issue with moving the keyboard when using multiple screens with different DPI.

For example, Screen 1 has a resolution of 2560x1440 and is set to "125% scale" in Windows display settings. Screen 2 is 1920x1080 and is set to "100% scale".

Open the Windows app compatibility settings of the hvk.exe file and set the DPI behavior to "Application", which means that the application manages all DPI-related calculations. With this setting activated, you can pass physical pixel values to the move function of your API, and the keyboard window is then moved to exactly that position.

If you want to activate this compatibility mode programmatically (e.g., with your own installer), you have to set the following registry key:

HKEY_LOCAL_MACHINE\SOFTWARE\Microsoft\Windows

NT\CurrentVersion\AppCompatFlags\Layers:

"C:\Program Files\HotVirtualKeyboard\hvk.exe"="~ HIGHDPIAWARE"

This will then apply to all users. Alternatively, you can place this key in the registry for the current user

(HKCU).

6.2 How to lock all settings

Developers can lock all settings to prevent the end user from change them.

- 1. Open the HKEY_CURRENT_USER\Software\ComfortSoftware\hvk registry key, add a DWORD parameter named **AccessDenied**, and set its value to **1**.
- 2. Restart the application.

Note: You can easily set the value of the AccessDenied parameter by using the following files from the application installation folder: *AccessAllowed.reg* and *AccessDenied.reg*

Note: If you want to be able to <u>close, move, and zoom</u> the on-screen keyboard, set the value of the **AccessDenied** parameter to **2**.

See Also

Command line parameters

6.3 How to activate different keyboards

You can specify different types of on-screen keyboards to be displayed. Please use any of the following methods.

Method 1

Change the **KeyboardName** registry parameter at HKEY_CURRENT_USER\Software\ComfortSoftware\hvk from your software.

Method 2

Download this file: https://hotvirtualkeyboard.com/files/SetNameKB.exe

Command line format: SetNameKB.exe KeyboardName

For example: SetNameKB.exe Mini

Method 3

Use this code:

```
char KeyboardName[80];
COPYDATASTRUCT MyCDS;

KeyboardName = "Standard";

// Fill the COPYDATA structure

MyCDS.dwData = 1; // function identifier

MyCDS.cbData = sizeof(KeyboardName); // size of data

MyCDS.lpData = &KeyboardName; // data structure

// Call function, passing data in &MyCDS

HWND hwDispatch = FindWindow( "TFirstForm", "hvkFirstForm" );
if( hwDispatch != NULL )
```

```
SendMessage( hwDispatch,
  WM_COPYDATA,
  (WPARAM)(HWND) NULL,
  (LPARAM) (LPVOID) &MyCDS );
```

6.4 FAQ for developers

How can I include the on-screen keyboard into my own installer?

1) Copy the following set of files to the end users' computers:

hvk.exe

hvkcm.exe

hvkcm64.exe

hykh dll

hvkh64.dll

bass.dll

COptions.exe

Keyboards – the folder containing on-screen keyboards (one text file per keyboard)

Lang – the folder with the application's interface translated into different languages

Skins – the folder with skin images

Background – (optional) the folder containing images for the keyboard background

Icons – (optional) the folder containing shortcut icons for different applications

Sound – (optional) the folder containing Wav files

hvkDeskBand.dll, hvkDeskBand64.dll – (optional) the DLL files for displaying the application's toolbar in the taskbar

Common – (optional) the folder containing predefined data on word frequency and word order for the most popular languages

- *.dic Text Suggestions dictionaries. The folder for storing these dictionaries is specified in the **Data directory** field in the **Dictionaries** section of the application's settings. If you prefer, you can move dictionary files to the application installation folder.
- 2) If you turned on the displaying of the on-screen keyboard prior to the system login: Backup.ini the pre-login settings file for the on-screen keyboard (Data folder) You also need to copy the following four files to the *Windows\system32* system folder: runcosk.exe, CsCredentialLogon.dll, CsCredentialLogon64.dll, and cskeyboardlogon.dll
- 3) If you have configured special shortcuts, you also need to copy the file for them to the same folder as on the source computer. You can find the full path and filename in the title of the Keyboard Shortcuts Settings window.
- 4) To transfer the application's settings, do the following:

Save the settings to a file. To do that, click the **Save to File...** button in the **Advanced** section of the **Settings** window.

After copying the ini-file to the end user's computer, start **hvk.exe** with the <u>/RESTORE</u> parameter. Command format: hvk.exe /RESTORE "file name"

For example: hvk.exe /RESTORE "C:\Program Files\HotVirtualKeyboard\Settings.ini"

How can I switch between several on-screen keyboards?

Add a key to each on-screen keyboard (in the <u>Edit Keyboard Type</u> window), and then assign the <u>Activate the next keyboard type</u> action to that key in the <u>Keyboard Shortcuts Settings</u> window. If you assign a keyboard switch action to the key, a button for configuring the list of switchable keyboards will be displayed.

How can I create a key with the ".com" text?

The easiest way to add special keys is by using the Edit Keyboard Type window.

- 1. Add a key to the on-screen keyboard via the <u>Edit Keyboard Type</u> window. You can use unassigned keys defined by a hexadecimal code (for instance, 00D9).
- 2. Select the key and press the **Action...** button. In the new <u>Keyboard Shortcuts Settings</u> window, assign the **Paste text** action to that key. Enter your text (in this case, ".com") into the **Text** field. Set the **Show text on the on-screen keyboard** checkbox under the **Text** field as desired.

After configuring these settings, save them and close the window.

Can I configure the pre-login on-screen keyboard to be different from the regular one, used after the login?

The settings of the on-screen keyboard for entering the login password are stored in the *Backup.ini* file, located in the application installation folder (in the *Data* subfolder). When you change the application's settings in the <u>Settings</u> window, they are saved in the *Backup.ini* file (and in the registry). If you don't want the *Backup.ini* file to change, make it "Read-only."

How can I paint keyboard keys in different colors?

Select the necessary key in the <u>Edit Keyboard Type</u> window, click the **Picture / Color...** button, and then specify the color for each state in the **Color** fields.

How can I change keyboard parameters from my program?

Our application's settings are stored in the HKEY_CURRENT_USER\Software\ComfortSoftware\hvk registry key.

If your software changes any of these settings in the system registry, our application will need to load them again. It can be done by sending a windows message containing the WM_USER + 196 code to our application:

```
WM_CSRELOADOPTIONS = WM_USER + 196;
PostMessage(FindWindow('TFirstForm', 'hvkFirstForm'), WM_CSRELOADOPTIONS, 0, 0);
```

This command allows you to do the following:

- Change the interface language (labels on system keys) according to the current input language
- Change the keyboard transparency
- Change the keyboard size
- Temporarily disable the Show the on-screen keyboard when the text cursor is visible option
- Temporarily disable the Text Suggestions feature
- Change the limitation on access to our application's settings without reloading the program

How can I transfer your application's settings and data to another computer?

Sorry, you cannot do it in one click.

You will have to do the following:

- 1. Save the general settings: All Settings -> Advanced -> Save to File...
- 2. Save the keyboard file (the name of the file and its full path can be found in the caption of the Edit Keyboard Type window).
- 3. Save the hotkey settings file (you can find its name and full path in the title of the <u>Keyboard Shortcuts</u> <u>Settings</u> window).
- 4. Restore all these data on the target computer.

The application doesn't start and shows an error message each time I try to run it!

- 1. Our application works on Windows 2000 or above only. Sorry, but Windows 95, Windows 98 and Windows CE are not supported.
- 2. Maybe some of the application's components have not been installed. Please try reinstalling the application.
- 3. Make sure to install the application to the **Program Files** folder. It's a security-related requirement for new operating systems.

6.5 Command line parameters

Hot Virtual Keyboard (hwk.exe) accepts optional command line parameters. These parameters can be useful for developers and for calling our application from other software.

/HELP and /?

Displays the list of valid command line parameters in a message box.

/CLOSE

Closes a previously launched instance of the application.

/SHOWKEYBOARD

Forcibly shows the on-screen keyboard when the application is launched. Normally, the on-screen keyboard is shown only if it was visible the last time the application was closed.

/HIDEKEYBOARD

Starts the application with the on-screen keyboard hidden. Normally, the on-screen keyboard is shown if it was visible the last time the application was closed.

/COMMON

Starts the application with the same settings for all users.

This parameter instructs the application to save its settings to the following registry key:

HKEY_LOCAL_MACHINE\SOFTWARE\ComfortSoftware\hvk

Normally, they are saved to this registry key:

HKEY_CURRENT_USER\SOFTWARE\ComfortSoftware\hvk

/INIFILE

Instructs the application to save and read its settings from the INI file. Normally, the settings are stored in the registry.

The settings will be stored to the *Backup.ini* file located in the application installation folder (in the *Data* subfolder).

How to use:

Save your settings to "C:\Program Files\HotVirtualKeyboard\Data\Backup.ini" file, and launch "hvk. exe /INIFILE". In this case, the application saves and reads the settings from the Backup.ini file.

/OPTIONS

Opens the application settings window.

/CHANGELANGUAGE < code >

Changes the current system language. If you use this parameter without specifying an input language code, the program will switch the input language or layout to the next one.

For example: "C:\Program Files\HotVirtualKeyboard\hvk.exe" /CHANGELANGUAGE 0409

/RESTORE

Instructs the application to load settings from the INI file specified in the command line. If another instance of the application is already running, the settings from the INI file will be loaded into it. You can save the settings to the INI file by opening the **Settings** window and switching to the **Advanced** section

For example: "C:\Program Files\Hot\VirtualKeyboard\hvk.exe" /RESTORE "C:\Program Files\Hot\VirtualKeyboard\Settings.ini"

/M <num>

Launches several instances of the program, where *<num>* is the number of instances to be launched. Each instance will have its own settings. By default, you can launch one instance only.

/TURNON and /TURNOFF

Completely turn the application on or off. Use the /SHOWKEYBOARD or /HIDEKEYBOARD parameter to show or hide the on-screen keyboard.

/ACTION <hotkey>

Launches the action assigned to the specified hotkey.

For example: "C:\Program Files\HotVirtualKeyboard\hvk.exe" /ACTION Win+K

You can specify a key code in the hexadecimal format by using \$ (the dollar sign). For example, \$20 is Space, and \$1B is Escape.

For example: "C:\Program Files\HotVirtualKeyboard\hvk.exe" /ACTION Alt+\$20

/SAFEMODE

Launches the application in safe mode. Some features of the application will be disabled.

/DEBUG

Instructs the application to create the *Log.txt* file in the application folder (in the *Data* subfolder). The log file will contain details about the application's activity, which can be a helpful debugging aid. The information contained in the log file is technical in nature and therefore not intended to be understandable by end users.

If a file with the specified name already exists in the application folder, it will be overwritten.

/EVENTLOG

Instructs the application to create different log files for every startup. See the *Data* subfolder in the application folder.

You can also add the DWORD parameter EventLog=1 in the registry to do the same.

/REMOTECONTROLMODE

Enables the special mode for remote control devices. In this mode, you can use the arrow keys to move around the keyboard, and use **Enter** key to press the currently selected key.

7 Other issues

FAQ - Frequently asked questions

Please read this topic if you have a problem with activating or using Hot Virtual Keyboard.

License Agreement

Hot Virtual Keyboard End User License Agreement.

Contact information

Comfort Software Group contact details.

7.1 FAQ - Frequently asked questions

Hot Virtual Keyboard usage issues

Q: Your application doesn't react to any key combinations at all.

A: Maybe that's because another hotkey manager is running? Otherwise, please make sure that Hot Virtual Keyboard is turned on.

Q: If I run Setup Wizard again, will it delete all my previously created actions?

A: No, it will not. All your actions will be preserved. Setup Wizard will simply add more shortcuts to your set.

Q: Can I deactivate a key on my keyboard?

A: Yes, you can. Just create an action with the Block key or shortcut action type.

Q: How can I install another language and keyboard layout?

A: Follow these steps:

- 1. In the Windows Start menu, click **Start**, and then click **Control Panel**.
- 2. Double-click Regional and Language Options.
- 3. Click the Languages tab, and then click Details under "Text Services and Input Languages."
- 4. Click *Add* under "Installed Services," then click the language that you want to add, and then select the keyboard layout that you want to use for that language.

Q: How can I transfer the application's settings and data to another computer?

A: Sorry, you cannot do it in one click. You will have to do the following:

- 1. Save the general settings: Parameters -> Advanced -> Save to File...
- 2. Save the hotkey settings file (you can find its name and full path in the title of the <u>Keyboard Shortcuts Settings</u> window).
- 3. Restore all these data on the target computer.

Q: The application doesn't start and shows an error message each time I try to run it!

A: Please check this:

- 1. Maybe some of the application's components have not been installed. Please try reinstalling the application.
- 2. Make sure to install the application to the **Program Files** folder. It's a security-related requirement for new operating systems.

Q: Can I use the Sleep key in a shortcut?

A: No, you cannot. The **Wake**, **Sleep**, and **Power** keys cannot be used as a hotkey or part of a key combination for any action.

Q: Can I use Hot Virtual Keyboard on a network, so that all users can get the same results for key presses?

A: Yes. You can place your actions file on a network resource and open it on any workstation.

Q: Does Hot Virtual Keyboard support a "send email" action type?

A: Yes, it does. Create the **Run program** action and enter "mailto:" followed by the recipient's email address.

Q: Can I use "Open URL" for FTP or Telnet?

A: Yes, you can. When creating an action, enter an URL like ftp://ftp.mycompany.com or telnet://

mycompany.com in the Open URL text field.

Licensing issues

Q: How to check if your software product is licensed?

A: To see the license information, select About Hot Virtual Keyboard in its context menu.

Q: How do I activate the software?

A: You need to enter your product key on each computer where the software is used. The trial version becomes activated when you enter the product key, so you don't need to download and install the program again. The activated version does not show a purchase reminder on the program startup. So if you do everything right, you should not see that reminder, and your license information appears in the About dialog box.

7.2 License Agreement

HOT VIRTUAL KEYBOARD LICENSE A GREEMENT FOR USE AND DISTRIBUTION

Last updated April, 2021

READ THE TERMS OF THIS SOFTWARE LICENSE AGREEMENT (HEREINAFTER THE "AGREEMENT") CAREFULLY. BY DOWNLOADING, INSTALLING, IMPLEMENTING OR USING THIS SOFTWARE PRODUCT, YOU AGREE TO THE TERMS AND CONDITIONS OF THIS AGREEMENT. YOU AGREE THAT THIS AGREEMENT IS ENFORCEABLE AS ANY WRITTEN AGREEMENT NEGOTIATED AND SIGNED BY YOU AND COMFORT SOFTWARE GROUP (HEREINAFTER "COMFORTSOFTWARE"). IF YOU ARE ACCESSING SOFTWARE ELECTRONICALLY, INDICATE YOUR ACCEPTANCE OF THESE TERMS BY SELECTING THE "ACCEPT" (OR EQUIVALENT) BUTTON. IF YOU DO NOT AGREE TO ALL OF THE TERMS, PROMPTLY RETURN THE UNUSED SOFTWARE TO YOUR PLACE OF PURCHASE FOR A REFUND OR, IF SOFTWARE IS ACCESSED ELECTRONICALLY, SELECT THE "DECLINE" (OR EQUIVALENT) BUTTON.

NOW, THEREFORE, IN CONSIDERATION OF THE MUTUAL PROMISES SET FORTH HEREIN, COMFORTSOFTWARE AND YOU HEREBY AGREE AS FOLLOWS:

DEFINITIONS:

- (a) "**You**" shall mean the individual using, implementing, downloading, or installing the underlying Software. In the event You are using, implementing, downloading, or installing the underlying Software on behalf of an Organization, all liability for a breach of this agreement shall be the responsibility of said Organization.
- (b) "**Licensee**" shall mean You together with any Organization You may be representing, or any related agent, employee, or representative of You or such Organization that has downloaded, used, installed, or implemented the software package on Your behalf or on behalf of such Organization.
- (c) "**Software**" shall mean any and all computer programs produced, created, developed, or provided by COMFORTSOFTWARE, including, but not limited to, applicable programs, fonts, components, hosted services, source code, modules, corresponding documentation, updates, upgrades, or modifications thereto.
- (d) "**Developer**" shall mean an individual who has a primary job function of developing software applications.
- (e) "**Server**" shall mean a computer system that multiple users access or make use of, including but not limited to, terminal servers, file servers, application servers or web servers.
- (f) "**Effective Users**" shall mean the number of users that are effective for software licensing, which is determined by the following method that returns the greatest number: (1) The number of computers on which the Software is installed, or (2) where the Software is used on a Server or run from a Server, the number of users per week that have access to the Software on the Server.
- (g) "**Organization**" shall mean a single company, business unit, government organization, entity or individual. In this Agreement, each subsidiary of a company or business unit with a separate Tax ID is considered a separate Organization.

(h) "**User**" shall mean a single person that is making use of the Software.

TERMS:

1. License Grant

In consideration for the license fee paid, and other good and valuable consideration, COMFORTSOFTWARE grants to Licensee only, unless otherwise limited by the license purchased or granted, the nonexclusive, nontransferable, perpetual, world-wide right to use the Software in accordance with this Agreement and the license defined herein that Licensee purchases ("License"). If You are installing, accessing or using this Software for Your employer, this Agreement also includes Your employer. Licensee may only use the Software according to the License purchased or granted by COMFORTSOFTWARE. COMFORTSOFTWARE offers several license types to meet the needs of different Organizations and implementations. Particular Licenses are offered for each product depending on the intended use of the Software. COMFORTSOFTWARE offers some Licenses that are granted to Licensee by this Agreement and not purchased; these include the Optional Integration License, Evaluation License, Free License and the Beta License.

A. Single User License

The Single User License allows use of the Software for one User in Licensee's Organization according to Effective Users.

Home users may use their single computer usage license on two (2) computers which are in property of the license owner.

B. Multiple User Licensing

Multiple user licenses grant the rights of the Single User License for a particular number of Effective Users. For example, a 5 User License grants the rights for 5 Single User Licenses. These licenses may be combined; for example, 1 Single User License and a 10 User License = 11 licensed users.

- **C. Site License** allows use of the Software for all users at a single site within a single Organization. Because of the discounts associated with this license, technical support is provided to a single technical contact at Licensee's Organization instead of to each individual user.
- **D. Enterprise License** allows use of the Software for an unlimited number of users at an unlimited number of sites within a single Organization. Because of the discounts associated with this license, technical support is provided to a single technical contact at Licensee's Organization instead of to each individual user.

E. Developer License

Developer License allows royalty-free distribution and use of the Software internally (in the same Organization) and externally (outside the Organization) for an unlimited number of developers and up to 5000 user licenses according to Effective Users, provided Licensee adheres to the Developer License Distribution Terms.

F. Developer License Distribution Terms

As used in this section, the term ("User Licenses") shall mean the number of Users that Licensee's License allows according to the definition of Effective Users. The Developer License allows 5000 Effective Users.

(a). Internal Distribution:

Allows use of the Software in Licensee's Organization, provided Licensee does not exceed its User Licenses and Licensee adheres to the following terms:

- (1) If distribution of Licensee's application exceeds its User Licenses, additional Developer Licenses are required; each Developer License purchased will allow distribution of an additional 5000 Effective Users.
- (2) The Software may be used on any number of Servers, provided that the number of users accessing all of the servers does not exceed Licensee's User Licenses.

(b). External Distribution:

Allows Licensee to rent, lease or distribute the Software outside its Organization bundled with an

application, provided Licensee does not exceed its User Licenses and Licensee adheres to the following terms:

- (1) Licensee may not resell, rent, lease or distribute the Software alone. The Software must be distributed as a component of an application and bundled with an application or with the application's installation files. The Software may only be used as part of, and in connection with, the bundled application. Licensee may embed the Software into Licensee's firmware, provided a copyright notice is added in the firmware or documentation as detailed in number 4 of this section.
- (2) Licensee may not resell, rent, lease, distribute or otherwise use the Software for the License that was purchased, in any way that would compete with COMFORTSOFTWARE. If it is determined by COMFORTSOFTWARE or Licensee that Licensee's distribution or use of the Software competes with COMFORTSOFTWARE, a reasonable royalty fee for Licensee's distribution or use of the Software must be negotiated and agreed to by Licensee and COMFORTSOFTWARE and paid to COMFORTSOFTWARE each quarter or another agreed upon interval of time.
- (3) If Licensee uses the Software internally within its Organization, Licensee shall deduct the quantity of its User Licenses used within its Organization from the total number of its User Licenses that are distributed outside its Organization. For example, if Licensee has a One Developer License and uses 1,000 User Licenses internally, it may only distribute up to 4,000 User Licenses outside its Organization.
- (4) A valid copyright notice must be provided within the user documentation, start-up screen or in the help-about section of Licensee's application that specifies COMFORTSOFTWARE as the provider of the Software bundled with its application, for example: "<<your application name>> contains software components licensed from Comfort Software Group. These products may only be used as part of and in connection with <<your application name>>."
- (5) At no time may Licensee create any tool or product that directly or indirectly competes with any COMFORTSOFTWARE products.

2. Trial version

The software unlicensed trial version may be freely distributed, with exceptions noted below, provided the distribution package is not modified in any way.

- (a) No person or company may distribute separate parts of the package without written permission of the copyright owner.
- (b) The software unlicensed trial version may not be distributed inside of any other software package without written permission of the copyright owner.
- (c) Hacks/cracks, keys or key generators may not be included on the same distribution.

3. Copyright

By downloading, installing, using, or implementing this Software, Licensee acknowledges COMFORTSOFTWARE's assertion of a copyright in the underlying software and code. The Software and the accompanying materials are licensed, not sold, to Licensee. COMFORTSOFTWARE maintains ownership of all copyright interests in the Software, including any derivative works based upon the Software, and excluding any application bundled with the Software by Licensee in accordance with this Agreement. Licensee may not rent, lease, display or distribute copies of the Software to others except under the conditions of this Agreement. Unauthorized copying of the Software or accompanying materials even if modified, merged, or included with other software, or of the written materials, is expressly forbidden. Licensee may be held legally responsible for any infringement of intellectual property rights that is caused or encouraged by Licensees failure to abide by the terms of this Agreement. Licensee may make copies of the Software as needed for development and use provided that the number of copies made do not exceed the number of users allowed by the License purchased. Licensee may also make a reasonable number of archival copies of the Software for backup and recovery purposes and may temporarily use the backup copy, including but not limited to during emergency situations, disaster recovery, or disaster recovery tests. In any case, when a copy is created, any copyright notices included in the Software must be reproduced in their entirety on the copy.

4. Software Modifications

If the Developer License is purchased, Licensee may modify any portions of the Software as needed, provided that copyright notices are not removed.

5. Agreement Duration and Termination

Subject to the terms and conditions of this Agreement, this Agreement begins when the Software is downloaded, installed, used or when a License for Software is purchased or granted and is perpetual unless terminated in accordance with this Agreement. When the Agreement begins, this Agreement shall supersede all older versions of this Agreement including any older Agreements that may be embedded in the Software. This Agreement shall inure to the benefit of and be binding upon COMFORTSOFTWARE and Licensee. Licensee may terminate this Agreement at any time by returning the Software to COMFORTSOFTWARE and destroying all copies thereof. This Agreement shall terminate upon notice from COMFORTSOFTWARE if Licensee fails to comply with any provision contained herein or if the funds paid for the license are refunded or are not received, and such failure or breach is not cured within thirty (30) days of such notice. Upon termination, Licensee must destroy the Software and all copies (in part and in whole, including modified copies, if any) in its possession or control. COMFORTSOFTWARE reserves the right to terminate this Agreement if the use of Software by Licensee causes a loss of revenue for COMFORTSOFTWARE that exceeds ten (10) times the amount Licensee paid for the License. Termination of this Agreement shall not affect the Software bundled and distributed with an application under the Developer License by Licensee prior to termination, provided Licensee has purchased a Developer License for the Software, the bundled application does not compete with COMFORTSOFTWARE in any way, and funds for the License were received and not returned or refunded in any way. All restrictions prohibiting Licensee's use of the Software and intellectual property provisions relating to Software to the benefit of COMFORTSOFTWARE shall survive termination of this Agreement.

6. Updates

COMFORTSOFTWARE offers free Major upgrades for a period of thirty (30) days from the date of purchase.

All Minor version updates are free. For example, if you purchased a license for version 9.0, it will work with version 9.1, but will not work with 10.0. You can purchase upgrade to the next Major version at a reduced price. In either case you can continue to use your existing license for as long as you like.

7. Limited warranty

A. Limited warranty

If you follow the instructions, the software will perform substantially as described in the COMFORTSOFTWARE materials that you receive in or with the software.

B. Term of warranty; warranty recipient; length of any implied warranties

The limited warranty covers the software for one year after acquired by the first user. If you receive supplements, updates, or replacement software during that year, they will be covered for the remainder of the warranty or 30 days, whichever is longer. If the first user transfers the software, the remainder of the warranty will apply to the recipient.

To the extent permitted by law, any implied warranties, guarantees or conditions last only during the term of the limited warranty. Some states do not allow limitations on how long an implied warranty lasts, so these limitations may not apply to you. They also might not apply to you because some countries may not allow limitations on how long an implied warranty, guarantee or condition lasts.

C. Exclusions from warranty

This warranty does not cover problems caused by your acts (or failures to act), the acts of others, or events beyond COMFORTSOFTWARE's reasonable control.

D. Remedy for breach of warranty

COMFORTSOFTWARE will repair or replace the software at no charge. If COMFORTSOFTWARE cannot repair or replace it, COMFORTSOFTWARE will refund the amount shown on your receipt for the software. It will also repair or replace supplements, updates and replacement software at no charge. If COMFORTSOFTWARE cannot repair or replace them, it will refund the amount you paid for them, if any. You must uninstall the software and return any media and other associated materials to COMFORTSOFTWARE with proof of purchase to obtain a refund. These are your only remedies for breach of the limited warranty.

E. Consumer rights not affected

You may have additional consumer rights under your local laws, which this agreement cannot change.

F. Warranty procedures

You need proof of purchase for warranty service. For warranty service or information about how to obtain a refund for software, contact COMFORTSOFTWARE at https://hotvirtualkeyboard.com/contact/.

G. No other warranties

The limited warranty is the only direct warranty from COMFORTSOFTWARE. COMFORTSOFTWARE gives no other express warranties, guarantees or conditions. Where allowed by your local laws, COMFORTSOFTWARE excludes implied warranties of merchantability, fitness for a particular purpose and non-infringement. If your local laws give you any implied warranties, guarantees or conditions, despite this exclusion, your remedies are described in the Remedy for Breach of Warranty clause above, to the extent permitted by your local laws.

H. Limitation on and exclusion of damages for breach of warranty

The Limitation on and Exclusion of Damages clause above applies to breaches of this limited warranty.

This warranty gives you specific legal rights, and you may also have other rights which vary from state to state. You may also have other rights which vary from country to country.

Comfort Software Group

7.3 Contact information

Web-site: https://hotvirtualkeyboard.com/

User support: support@hotvirtualkeyboard.com

Index

- A -

Action types Audio control 24 Block shortcut 26 Change the language or case Connect/Disconnect from a network 24 Hot Virtual Keyboard actions 21 Lock/Restart/Shutdown Monitor control Open one or several Internet resources 24 Operations with windows Paste text Perform a system action 25 22 Play a keystroke macro Replace shortcut Run a program, open a document or folder 23

- C -

Command line parameters 36
Contact information 43
Customizing the keyboard type 4

- E -

Editing shortcut icons 8

- F -

FAQ - Frequently asked questions 38

- H -

How to buy Hot Virtual Keyboard 1 How to use Hot Virtual Keyboard 2

- | -

Introducing Hot Virtual Keyboard

- K -

Keyboard shortcuts settings 3

- L -

License Agreement 39

- S -

Settings Advanced 21 11 Appearance Theme Dependencies Floating Window General 10 Gestures 16 Keys 12 Language Bar 19 Position 14 Shortcut Icons 20 Show/Hide 13 20 Sounds System 9 Text Suggestions 17 Typing Aid 15 Zoom 14 Support 43

- T -

Text tags 7

- U -

Using the on-screen keyboard